

Skagit Stout

320 E Fairhaven, Burlington WA, 98233 360-293-0424



Dry Irish Stout

Jet black stout, with complex coffee-like aromas from the roasted malts. Creamy, long-lasting head.

OG=1.051, FG=1.013, ABV=5.1%, IBU=36

KIT INVENTORY

*Store liquid yeast and Hops in the refrigerator

Steeping grains:

.75 lb. Roasted Barley

.25 lb. Crystal 60

.25 lb. Black Malt

Extracts:

6.6 lb. Golden Light malt extract (LME)

Hops:

1 oz. Northern Brewer (60min)

1 oz. East Kent Goldings (5min)

Recommended Yeasts:

Wyeast 1084

Imperial Labs Darkness

Bottling Primer:

5 oz. Priming Sugar (Corn Sugar)

BREWING INSTRUCTIONS

(Read completely before brewing)

1. If using, activate the liquid yeast culture (see directions on back) and weigh out hops if necessary.
2. Start with 3 gallons of water at 150-160°F in the brew kettle. Steep the **bag of grains** for 30 minutes. After 30 min. remove the grain bag and discard.
3. Add all extracts to the kettle. To avoid scorching, do your best to fully dissolve extracts before applying direct heat. You now have wort (unfermented beer), bring

your wort to a boil (watching carefully for a boil over).

4. Add **1 oz. Northern Brewer** and set timer for **60** minutes.
5. With **5** minutes remaining, add hop packet **1 oz. East Kent Goldings**
6. After the 60-minute-long boil, remove kettle from heat, cover with lid and cool as quickly as possible to 100°F. Use a wort chiller or make an ice bath in your sink.
7. Fill your sanitized primary fermenter with 2 gallons of cold water, and then add your 100°F wort. Using additional cold water, top up the volume to 5 gallons.
8. Add (pitch) **yeast** when the temperature of the wort is between 65 and 72°F. Stir or shake well to oxygenate your wort.
9. Affix a sanitized airlock into your primary fermenter, allow to ferment in the dark for 7-10 days. Do your best to ferment within the temperature range of your yeast.
10. Take a gravity reading to confirm it is finished fermenting. It should match your final gravity or **F.G.** Transfer (rack) the beer by siphoning to a 5-gallon secondary fermenter. This will allow your beer to finish conditioning and clearing. (approx. 1-2 weeks).
11. Prepare to bottle by boiling 5 oz. of **priming sugar (Corn sugar)** in 1 pint of water, pour this mixture into the bottling bucket.
12. Transfer your beer into the bottling bucket by siphon, stir gently to incorporate the priming sugar evenly (avoid splashing). Fill and cap bottles immediately.

13. Allow the bottles of beer to rest at room temperature for 10 -14 days to carbonate, then cool and enjoy!!

TIPS & TRICKS

We recommend boiling your hops in a hop bag (muslin sock) or straining them out before primary fermentation.

Adding Irish moss or Whirlfloc to your boil for the last 15 min. is a nice touch for better clarity, but not essential. (Not included in kit)

Popular Options:

Add 1lb Lactose to the boil for a milk stout. Add 1lb, Flaked Oats, to the mash for an oatmeal stout.

Add 4oz. Cocoa Nibs in secondary for a chocolate stout.

Notes: _____
